

# Uninstalling Cisco VPN

1. First, run the Cisco Secure Client application

To obtain the UCI cisco secure client, go to

[oit.uci.edu/vpn](http://oit.uci.edu/vpn)

Home > Knowledge > Knowledge (Knowledge Base) > Security - Secure Computing

Search

KB0012170 - Latest Version

Actions

## Download the Cisco Secure Client

Revised by Mike Caban • 4mo ago • 4508 Views

### Download, install and configure the Cisco Secure Client

- o **macOS** - Compatible with **macOS 13, 14 and 15 (Ventura, Sonoma, and Sequoia)**
- o **Windows** - Compatible with **Windows 10 and 11**
- o **Linux** - Compatible with **Ubuntu 20.04 and Ubuntu 24.04**
- o **Chromebook**

### VPN Software Version

The current version of the Cisco Secure Client for all platforms is **5.1.4.74**.

Peer-to-peer file sharing services and other high-bandwidth applications should not be used while using the VPN service. You may be automatically blocked from using the VPN if your bandwidth exceeds the maximum bandwidth limit.

Copy Permalink

Also in S

Download  
4508 Views

Download  
for Andro  
613 Views

VPN: On r  
are graye  
509 Views

How to in  
Secure Cl  
250 Views

How to cc  
VPN for A  
234 Views

View all 1

OIT Help Desk (949) 824-2222

Office of Information Technology, UC Irvine

Copyright © 2025 UC Regents. All Rights Reserved

2. Once you download cisco secure client, run the "un-install cisco secure client"

▼ Cisco	Jan 24, 2025 at 9:53 AM	--	Folder
📄 Cisco Secure Client	Jan 24, 2025 at 9:53 AM	11.9 MB	Application
📄 Cisco Secure Client - DART	Jan 24, 2025 at 9:53 AM	7.1 MB	Application
📄 Cisco Secure Client - Socket Filter	Jan 24, 2025 at 9:53 AM	3.5 MB	Application
📄 <b>Uninstall Cisco Secure Client</b>	Jan 24, 2025 at 9:53 AM	438 KB	Application
📄 Uninstall Cisco Secure Client - DART	Jan 24, 2025 at 9:53 AM	438 KB	Application

**3. Open up the terminal program on your mac. You can search and find the "terminal" by click on the magnifying glass on the top right of your screen.**

Then run these commands in Terminal to completely remove all remaining Cisco Secure Client files:

```
sudo rm -rf /Library/Application Support/Cisco  
sudo rm -rf /opt/cisco*  
sudo rm -rf /Library/LaunchDaemons/com.cisco*
```

4. Restart your computer

5. Install the Cisco Secure client and follow OIT's instructions

[https://uci.service-now.com/sp?id=kb\\_article\\_view&sysparm\\_article=KB0010200](https://uci.service-now.com/sp?id=kb_article_view&sysparm_article=KB0010200)

---

Revision #9

Created 2025-03-03 18:16:49 UTC by Scott Pham

Updated 2025-03-03 19:12:08 UTC by Scott Pham